1. ERIC™ Requirements

HARDWARE/SOFTWARE	MINIMUM REQUIREMENT
CPU	Pentium or faster computer (300MHz minimum)
Monitor / Minimum Resolution	Super VGA / 1024X768 resolution minimum
Random Access Memory (RAM)	Minimum of 1 GB
CD-ROM	Any Speed
Hard Disk Space	Minimum of 100 MB
Operating Systems	Microsoft Windows XP SP3
	Microsoft Windows 7
	Microsoft Windows 8.1
Support Software	Microsoft Access Database Engine 2010
Printer	Any Windows compatible printer

Microsoft® and Windows® are registered trademarks of Microsoft Corporation

WARNING: The ERIC Application may not install or function correctly if the above system requirements are not satisfied.

ERIC requires the 'Microsoft Access Database Engine 2010' software to function. If this component is missing, the ERIC Installation will prompt you to install it prior to installing the ERIC software. If you choose not to install the Microsoft Access Database Engine 2010 software, ERIC will abort the install.

2. Installing ERIC

WARNING: ERIC may not install or function correctly if the target system requirements described in section 1 are not satisfied.

ERIC will install onto a hard disk under the default target folder provided or a folder selection of the users choice. The folder chosen should ideally not exist on the system or, if the target folder does exist, it should be free of any files to prevent data and initialization files from being confused by ERIC.

WARNING: If you are going to re-install the application on an existing system, uninstall the existing application first by selecting:

- ➢ Control Panel
- ➢ Add/Remove Programs **or** Programs and Features
- ➢ ERIC
- ➢ Remove **or** Uninstall/Change

When uninstalling ERIC version 1.1 (& later versions), the ERICCodes.mdb database file will remain. This file contains saved data which will be preserved when a newer version of the ERIC software is installed.

2.1 ERIC Install

Please follow these instructions carefully to ensure a successful install:

To begin, place the ERIC Source Disk in the CD-ROM drive. A browser window will automatically display showing links to multiple language versions of the ERIC software. Click on the desired language of the ERIC software and a window will display containing the Setup program for the ERIC software. Double-click the file '**Setup ERIC Software**' and the install process will begin. If there are any problems with the installation, ERIC can be manually installed by following the steps below:

Launching Setup Manually

From My Computer or Windows Explorer, select the CD-ROM drive containing the ERIC Source Disk. For example, if the disk is in drive D:, do the following:

- ➢ Select the CD-ROM D: and double click the default.htm file
- ➢ A window will display showing language options, click on the desired language
- ➢ A window containing the SETUP file will be displayed
- ➢ Double-click on the 'Setup ERIC Software' fil**e**

The **ERIC Setup Wizard** will appear and guide you through the installation. If needed, you will first be guided through the 'Microsoft Access Database Engine 2010' installation. Follow the instructions on the screen to install the ERIC software.

ERIC installation is now complete.

2.2 Running the Application

After installation, you may run the application by doing either of the following:

➤ Click on the ERIC shortcut placed on your desktop, or
➤ Click START
➤ Click PROGRAMS
➤ Click ERIC
➤ Click on the ERIC shortcut